


Introduction to Neutron Spin Echo Spectroscopy

Laura-Roxana Stingaciu

ORNL is managed by UT-Battelle, LLC for the US Department of Energy



This manuscript has been authored by UT-Battelle LLC under Contract No. DE-AC05-00OR22725 with the US Department of Energy (DOE). The US government retains and the publisher, by accepting the article for publication, acknowledges that the US government retains a nonexclusive, paid-up, irrevocable, worldwide license to publish or reproduce the published form of this manuscript, or allow others to do so, for US government purposes. DOE will provide public access to these results of federally sponsored research in accordance with the DOE Public Access Plan (<http://energy.gov/downloads/doe-public-access-plan>).

This research used resources at the Spallation Neutron Source, a DOE Office of Science User Facility operated by the Oak Ridge National Laboratory.

THANK YOU, ORGANIZERS & SPEAKERS!



Argonne National Lab.

- Stephan Rosenkranz
- Jessica McChesney
- Chengjun Sun


Oak Ridge National Lab.

- Bianca Haberl
- Michael Manley
- Adam Aczel
- Keith Taddei

A BIG ROUND OF APPLAUSE FOR THEM , PLEASE 🙏

The neutron scattering event

(in the Fraunhofer approximation)



$$\vec{Q} = \vec{k}_i - \vec{k}_f \quad = \text{momentum transfer}$$

$$\Delta E = E_i - E_f = \hbar\omega = \text{energy transfer}$$

$$k = \frac{2\pi}{\lambda} \quad \text{neutron momentum}$$


$$E = \frac{(\hbar k)^2}{2m_n} \quad \text{neutron energy}$$

QENS: quasielastic neutron scattering

A limiting case of inelastic scattering, centered at $\omega = 0$ characterized by small energy transfers

Energy spectra = structural and dynamical information

$S(Q, \omega) = \text{dynamic structure factor}$




$$\Delta E = E_i - E_f$$

$$\Delta E \ll E_i$$

- elastic peak
- quasielastic line
- inelastic peaks

Neutron spectroscopy landscape

(methods to measure dynamics)



XTL, TOF, XTL-TOF, TOF-TOF, XTL-XTL, TOF-XTL, NSE

$1\text{meV} \sim 8\text{cm}^{-1} \sim 1\text{ps}$


$1\mu\text{eV} \sim 0.008\text{cm}^{-1} \sim 1\text{ns}$

$1\text{neV} \sim 8 \times 10^{-6} \text{ cm}^{-1} \sim 1\mu\text{s}$

Figure design by L.R. Stingaciu, ORNL

Neutron Spin Echo (NSE) - principle 1

Larmor precession



<http://xrayphysics.com/sequences.html>




Figure by L.R. Stingaciu, ORNL

- ❑ Larmor Frequency

$$\omega_L = |\gamma B|$$

- ❑ Neutron Gyromagnetic Ratio


$$|\gamma/2\pi| \approx 30 \text{ MHz/T}$$

- ❑ Accumulated phase


$$\phi = \omega_L t = \gamma_L B t = \gamma B l \frac{1}{v}$$

Neutron Spin Echo (NSE) - principle 2

Hann echo



https://en.wikipedia.org/wiki/Neutron_spin_echo



<https://www.oxfordneutronschool.org/2017/Lectures/Fouquet%20-%20Neutron%20Spin%20Echo.pdf>

Neutron Spin Echo – a quasielastic process




Figure design by L.R. Stingaciu, ORNL

inspired from Marcus Hennig: Dynamics of ...Studied by Neutron Scattering, 2011, Corpus ID: 91625454 and [FZJ-2015-04876] Open Access Book, Brückel, T. ; Richter, D. ; Roth, G. ; et al, Laboratory Course Neutron Scattering Lectures.

Neutron Spin Echo signal

$$I \sim \langle \cos \phi \rangle = \langle \cos \omega \tau \rangle$$

$$I \sim I(Q) \pm \int S(Q, \omega) \cos(\omega \tau) d\omega$$

Fourier transform
(Real part)

- $B \sim I(Q) = \text{static} = \text{structure factor}$


- $A \sim I(Q, \tau) = \mathcal{F}[S(Q, \omega)] = \text{amplitude of oscillation}$

- $$\frac{I(Q, \tau)}{I(Q, 0)} = \frac{2 A}{U - D}$$

Fourier time

$$\tau \cong 0.186 J \lambda^3 \text{ [ns]}$$

Example: $\lambda = 8\text{\AA}$, $J = 0.56 \text{ Tm} \rightarrow \tau \cong 50\text{ns}$
 $\rightarrow \Delta E \cong 0.01 \mu\text{eV} = 10 \text{ nanovolt}$






Energy and time domain QENS \leftrightarrow NSE

QENS: Dynamic Structure Factor

NSE: Intermediate Scattering Function


$$S(Q, \omega) \xleftarrow{\text{Fourier Transform}} I(Q, \tau)$$




$$I_D(Q, \omega) = S(Q, \omega) * R(Q, \omega)$$

$$I_D(Q, \tau) = I(Q, \tau) R(Q, \tau)$$

Coherent and incoherent scattering in NSE






$$I_{\text{up}} = I_{\text{coh}} + \frac{1}{3}I_{\text{inc}}$$



Flip Ratio

$$\text{FR} = \frac{I_{\text{up}}}{I_{\text{down}}}$$

Deuterium labeling and contrast variation



Neutron cross section is isotope dependent

Isotope	b
¹ H, Hydrogen	-3.7406(11)
² H, Deuterium	6.671(4)
³ H, Tritium	4.792(27)

Controlled mixing of ¹H and ²H allows contrast to be changed; very powerful for soft condensed matter.

Figure adapted by L. R. Stingaci, ORNL, from DOI:10.1016/j.csbj.2016.12.004

NSE spectrometers around the world




WASP @ ILL



IN15 @ ILL




J-NSE @ FRM II



RESEDA @ FRM II

Image sources: Institute Laue-Langevin, Grenoble, France and Research Reactor (FRM II) Munich, Germany


SNS-NSE, the Neutron Spin Echo spectrometer @ SNS



1 = neutron source; 2 = choppers-bender-polarizer-secondary shutter system; 3 = beam transport guides;
4 = $\pi/2$ flipper for first 90° spin-turn; 5 = first precession zone; 6 = π flipper for 180° spin-rotation;
7 = sample area and sample environment (cryo-furnace is shown here); 8 = second precession zone;
9 = $\pi/2$ flipper for second 90° spin-turn; 10 = analyzer; 11 = detector.

SNS-NSE sample environment & sample cells

Temperature Forcing
System (TFS),
275K - 400K



CCR , 5K - 700K



neutrons.ornl.gov/nse

SNS-NSE Data Reduction For Spin Echo Experiments

DrSPINE is a unified reactor - pulse source
NSE data reduction software

research papers



ISSN 1600-5767

Received 15 May 2019
Accepted 2 August 2019

Edited by Th. Proffen, Oak Ridge National Laboratory, USA

Keywords: neutron spin echo; NSE; spallation neutron sources; data reduction.

Supporting information: this article has supporting information at journals.iucr.org/j

Efficient data extraction from neutron time-of-flight spin-echo raw data

P. A. Zolnierczuk,^a O. Holderer,^b S. Pasini,^b T. Kozielewski,^c L. R. Stingaci^d and M. Monkenbusch^{c*}

^aForschungszentrum Jülich GmbH, JCNS Outstation, Oak Ridge, Tennessee, USA, ^bForschungszentrum Jülich GmbH, JCNS MLZ, Garching, Germany, ^cForschungszentrum Jülich GmbH, JCNS-1, Jülich, Germany, and ^dNScD, Oak Ridge National Laboratory, Oak Ridge, TN 37831, USA. *Correspondence e-mail: m.monkenbusch@fz-juelich.de

Neutron spin-echo spectrometers with a position-sensitive detector and operating with extended time-of-flight-tagged wavelength frames are able to collect a comprehensive set of data covering a large range of wavevector and Fourier time space with only a few instrumental settings in a quasi-continuous way. Extracting all the information contained in the raw data and mapping them to a suitable physical space in the most efficient way is a challenge. This article reports algorithms employed in dedicated software, *DrSpine* (data reduction for spin echo), that achieves this goal and yields reliable representations of the intermediate scattering function $S(Q, t)$ independent of the selected ‘binning’.



J-NSE Phoenix courtesy of Olaf Holderer, FRMII

SNS-NSE and TOF

- $\Delta\lambda = (5 - 8) \text{ \AA}$
- $2\theta = 3.6^\circ \quad Q = 0.02 - 0.15 \text{ \AA}^{-1}$
- $2\theta = 37^\circ \quad Q = 0.45 - 0.85 \text{ \AA}^{-1}$






Figure idea and cubes design by Piotr A. Zolnierczuk, 3D rendering by L.R. Stingaciu


Typical SNS-NSE data models

Simple Diffusion




$$\frac{S(q, \tau)}{S(q, 0)} = \exp(-D Q^2 \tau)$$

KWW



$$\frac{S(q, \tau)}{S(q, 0)} = \exp\left(-\left(\frac{\tau}{\tau_0}\right)^\beta\right)$$


Zilman-Granek



$$\frac{S(q, \tau)}{S(q, 0)} = \exp(-(\Gamma(q)\tau)^{2/3})$$

$$\Gamma(q) = \alpha \left(\frac{k_B T}{\kappa}\right)^{1/2} \frac{k_B T}{\eta} q^3$$

More complicated..



$$\frac{S(q, \tau)}{S(q, 0)} = [1 - \exp\left(-\left(\frac{qd}{6}\right)^2\right)] S_{\text{loc}} + \exp\left(-\left(\frac{qd}{6}\right)^2\right) S_{\text{esc}}$$

*Coherent dynamics in polymers,
glassy systems, bio-macromolecules*

Magnetic Dynamics, Spin glasses & spin fluids

Domain and allosteric motions in proteins

Shape fluctuations

SNS-NSE research highlights

dynamics of soft matter at nano- to meso-scale

Diffusion processes



**Short range translational, rotational and
tumbling diffusive motions**

Hydrogen jump diffusion

Interaction of solvent molecules with surfaces

SDS micelles in aqueous solution

J. Hayter, J. Penfold, J. Chem. Soc., Faraday Trans. 1, 1981, 77, 1851-1863, <https://doi.org/10.1039/F19817701851>




$$\frac{I(Q, t)}{I(Q, 0)} = e^{-D_{\text{eff}}(Q)Q^2 t}$$

$$D_{\text{eff}} = D_0 H(Q)/S(Q)$$

$$D_0 = \frac{kT}{6\pi\eta R} \quad \text{Stokes-Einstein}$$


Motions in entangled polymer melts

A. Wischnewski, M. Monkenbusch, L. Willner,... and D. Richter, Phys. Rev. Lett. **90** (2003), DOI: 10.1103/PhysRevLett.90.058302




$$\frac{S(Q, \tau)}{S(Q, 0)} = [1 - F(Q)] S^{loc} + F(Q) S^{esc}$$

- ❑ NSE Spin-Incoherent scattering measures proton self-correlation function
- ❑ Labeled long linear PEP polymer chain
- ❑ Segmental dynamics



Dynamics of phospholipid membranes

Sudipta Gupta, Piotr Zolnierzuk, Gerald J. Schneider, et al., *J. Phys. Chem. Lett.* 9, 2956 (2018), DOI: 10.1021/acs.jpclett.8b01008





Proposed mechanism of transient trapping and mean square displacement $\langle \Delta r(t)^2 \rangle_N$ as a function of Fourier time

- Friction at the interface water - liposomes plays a minor role
- The center of mass diffusion of liposomes and the transient trapping of lipids define the range in which ZG model can be applied

Proteins domains dynamics

L.R. Stingaciu et al., Sci Rep 6, 22148 (2016) <https://doi.org/10.1038/srep22148>


$$F(Q, t) = F_{trans}(Q, t) \cdot F_{rot}(Q, t) \cdot F_{int}(Q, t)$$





Three protein fragments in harmonic potential connected by flexible linkers

Spin dynamics in frustrated magnets

Yiyao Chen et al., iScience 24, <https://doi.org/10.1016/j.isci.2021.102206>



Polarization coils setup at SNS-NSE





Magnetic charges of $\pm Q$ unit and $\pm 3Q$ accumulate on the vertices of the honeycomb lattice

The charge defect relaxes between nearest neighbors

Neutron Spin Echo variations

Paramagnetic NSE

Sample is the π -flipper




http://sons.uniroma2.it/ericeneutronschool/wp-content/uploads/2016/12/NSE_MAgnetism_Pappas.pdf

Resonance, MIEZE, and SANS - spin echo

NRSE (Neutron Resonance Spin Echo)
T-NRSE or L-NRSE


<https://www-l1b.cea.fr/fr-en/pdf/muses-l1b.pdf>



RF field instead of solenoid
• compact design
• shorter Fourier times



SESANS
Spin Echo SANS

http://larmor.weblog.tudelft.nl/files/2013/07/S_Rogers_SANS_SESANS1.pdf




Spin Echo encoded SANS
• tilted magnetic field
• angle encoded in spin precession

Wide angle spin echo




<https://www.ill.eu/users/instruments/instruments-list/wasp/description/instrument-layout>



- ❑ Large angular coverage
- ❑ Higher Q (up to 3\AA^{-1})

EXPANSE, the wide-angle spin echo spectrometer at STS

- ❑ Expand the capability by another level: dual-functional instrument
- ❑ With the high-speed Fermi chopper, instrument can be used as a direct-geometry inelastic neutron spectrometer measuring $S(Q, \omega)$



Available wavelength	4 - 16 Å
Wavelength band	~4Å (15 Hz)
Detector solid angle	180° x 2.5° array of He ³ tube detectors
Momentum transfer range	0.05 – 3.14 Å ⁻¹
Fourier time range	30 ps – 90 ns (using 4 - 12Å)
Direct geometry mode	Energy resolution 10-300 µeV Incident energy range 0.5 – 9 meV (corresponds to 0.1 ps – 100 ps)

courtesy of Changwoo Do, ORNL

Summary – NSE technique in a nutshell

- NSE measures very small velocity changes using neutron spin precession in magnetic field
- Broad $\Delta\lambda/\lambda$ and high resolution
- Intermediate Scattering Function: $I(Q,\tau)$
- Complementary to SANS/SAXS
- Counting intensive and large or highly concentrated samples

Reference reading

- R. Pynn, Neutron Scattering, Neutron Spin Echo
http://www.iub.edu/~neutron/notes/20061204_Pynn.pdf
- F. Mezei (Ed.): Neutron Spin-Echo, Lecture Notes in Physics 128, Springer, 1980.
- F. Mezei, C. Pappas, T. Gutberlet (Eds.): Neutron Spin-Echo Spectroscopy, Lecture Notes in Physics 601, Springer, 2003.
- D. Richter, M. Monkenbusch, A. Arbe, J. Colmenero, Neutron Spin Echo in Polymer Systems, Adv. in Polymer Science 174, Springer, 2005
- M. Monkenbusch, D. Richter, High Resolution Neutron Spectroscopy
<http://doi.org/10.1016/j.crhy.2007.10.001>
- C.Pappas, G. Ehlers, F. Mezei, Neutron Spin Echo and Magnetism in Neutron Scattering from Magnetic Materials, ed. T. Chatterji, Springer 2006
- B.Farago, Basics of Neutron Spin-Echo, ILL Neutron Data Booklet,
https://www.ill.eu/fileadmin/users_files/documents/links/documentation/NeutronDataBooklet.pdf

THANK YOU

- ❑ The research highlights presented here used resources at the Spallation Neutron Source and High Flux Isotope Reactor, as part of the SNS-NSE spectrometer user program, DOE Office of Science User Facility operated by the Oak Ridge National Laboratory
- ❑ SNS-NSE spectrometer Team (P. A. Zolnierczuk & M. Odom)
- ❑ SNS and HFIR support groups
- ❑ SNS and HFIR user labs
- ❑ SNS and HFIR User Office
- ❑ US taxpayers



[Neutron Spin Echo Spectrometer | Neutron Science at ORNL](#)